



**elko**  
SYSTEMS

Installation Manual

---

## Contents


1. Pre-installation.....	3
2. Installing TeamViewer.....	3
3. Installing Sagem enrolment drivers .....	4
4. Installing DB2 .....	13
5. Linking to the server database.....	16
6. Setting the ODBC Connection .....	18
7. Windows 7/8 64-bit .....	24
8. Time Management.....	24

## 1. Pre-installation


Copy the files from the DVD to the C: drive on the pc.

## 2. Installing TeamViewer

1. Run the installation file from **C:\Elko Software\TeamViewer\_Setup.exe**
2. Select **Basic Installation**  
**Personal\Non-commercial use**  
**Show advanced settings**




3. Click **Accept – Next**
4. **Uncheck** all check boxes and click **Finish**



5. Check  
Start TeamViewer


## Assign device to account



6. Enter username: **elkohelpdesk@gmail.com**  
Password: **P@ssw0rd** with the 0 being a zero


## 3. Installing Sagem enrolment drivers

1. **DON'T** connect the enrolment reader until the installation is complete.
2. Open command prompt (**CMD**) as **administrator** and enter the following command:  
**bcdedit /set nx alwaysoff**




3. Run the installer as **administrator** found in **C:\Elko Software\Sagem (Window 8)\1. MorphoKit 5.3\MorphoKit\_5.3.exe** and follow the steps.


4. Select .Net Framework 4.0 when prompted to select a version.




5. When the installation is finished connect the enrolment reader.  
2 red LED's will flash until the drivers are detected. Once successfully installed a single green LED will flash.
6. Run the installer as **administrator** found in **C:\Elko Software\Sagem (Window 8)\2. MIK 6.0.12\setup.exe**
7. If the User Account Control prompts for permission, click Yes




8. Select **Install** to install Java updates and click **Yes**.



9. Close the java installer when it's finished.
10. If the following message appears stating that the java update failed, click **Yes** to continue the installation.




11. Ensure all the check boxes are checked.




12. On the following window check:


- Morpho License Manager 3.4
  - MorphoSmart USB Driver 3.58.1.1
- and click continue



13. Select **Copy an install service**.




14. After the license manager is installed wait a second for the USB driver to start installing and follow the steps.
15. When prompted to reboot the pc, select **Yes**. The reboot is required to start the license manager.







16. Open the System properties by right clicking on the **Start menu** and selecting **System**.




17. Select **Advanced System Settings**.



18. On the Advanced tab select **Settings**.



19. On the **Data Execution Prevention** tab select **Turn on DEP...**




20. Add the following:


- C:\Program Files(x86)\Sagem Securite\License Protection\SagemSeurite\_License\_Manager.exe
- C:\Program Files(x86)\Sagem Securite\License Protection\SagemSecure\_Licence\_Protection.exe

21. Apply the changes.

22. Open the Sagem License Manager to ensure all is running fine.  
Start Menu\All Programs\Manager 3.4.0 (GUI)




23. Ensure the **License in hardware** indicates **VERIF**.



24. Install the redistributables found in  
- C:\Morpho\MorphoKit\Redist\vc8redist\_x86\vc8redist\_86.exe  
- C:\Morpho\MorphoKit\Redist\vc10redist\_x86\vc10redist\_86.exe  
and follow the steps.
25. Register the dynamic link libraries by running the **three registration entries** found in  
C:\Morpho\MorphoKit\Deployment\

When prompted if you are sure, click **Yes**.



## 4. Installing DB2

Open the folder and run the file as administrator.


### Windows 64bit

C:\Elko Software\DB2 9.7.4\64-Bit\db2exc\_974\_WIN\_x86\_64.exe


### Windows 32bit

C:\Elko Software\DB2 9.7.4\32-Bit\db2exc\_974\_WIN\_x86.exe


Unzip the file.




Click OK



1. Select **Install a product**.
2. Click **Install new**.




Follow the installation steps (click next).




When prompted for a user account use the following credentials

- Enter **acta** to the User ID field.
- Enter **P@ssw0rd** in the password field with the 0 being a zero.



Close the **DB2 Setup Launchpad** window if it is still open.




## 5. Linking to the server database

1. Open the DB2 Control Center, which can be found in the Notification Bar in the bottom right corner, right click on the green circle.


This can also be found under the start menu

Start\All Programs\IBM DB2\DB2 Copy1\General Administration Tools\DB2 Control Center

2. Click on DB2 Control Center.




OR






3. Right click on **All Databases**.
4. Click **Add...**




5. Select the **Hostname** and the **Dropdown**. Click **Search** to display the list of available databases on the host server




6. Select the correct Database and enter a New Database alias.

## 6. Setting the ODBC Connection


1. Open the **Control Panel** which can be found on the start menu.




Alternatively select Run from the start menu or press the windows key and r simultaneously to open the Run window. Enter **control** and click OK.




2. Click on **Administrative Tools**.




3. Click on **Data Sources (ODBC)**.



Windows 8 have the 32-bit and 64-bit ODBC drivers together, we will need to run both




4. Windows 8 will ha
5. Select the **System DSN** tab page.
6. Click the **Add...** button.




7. Select the **IBM DB2 ODBC DRIVER**.


- Click **Finish**.




- Select **ACTA** from the Database Alias dropdown.
- Enter **ACTA** in the Data source name field.
- Click **OK**.



- Select the **ACTA System Data Source**.
- Click on **Configure**.



14. Add **acta** to the User ID field.
15. Add **P@ssw0rd** in the password field with 0 being a zero.
16. Check the **Save password** check box. And click OK when the warning message appears.
17. Click **Connect** to test the connection.
18. If the connection was made successfully click **OK**.




## 7. Windows 7 64-bit

If you have Windows 64-bit installed, you will have to add the System DSN again using the 32bit ODBC Data Source Administrator.

Open the Run window from the Start Menu, alternatively press the windows key and r simultaneously on the keyboard.

Enter **odbcad32** and click **OK**.



Now repeat steps 3.4 – 3.17

## 8. Time Management

Copy the Time Management Shortcut to the Desktop, the shortcut can be found in C:\Time Management\Time Management

